

PHEMI RESTful API User Guide

Contents

- REST Request Reference.....3**
 - User Login..... 3
 - User Logout..... 4
 - Data Ingest..... 5
 - Query Sensor Data.....8

- Semios DPF Reference..... 12**
 - DPF Metadata..... 12
 - DPF Processed Tags..... 14
 - DPF Processed Data..... 14

REST Request Reference

This section documents REST requests supported in the PHEMI RESTful API.

User Login

Log on to PHEMI Central and create an active session.

URI

```
POST /rest/user_sessions
```

Request Parameters

This request logs on to PHEMI Central by sending an HTTP POST request. The POST request expects valid user credentials in JSON format in the payload body, as in the following example.

```
{
  "username": "valid-username",
  "password": "valid-password"
}
```

Request Headers

None.

Response

The following are the HTTP status codes that can be expected:

201 Created

Successful login, the session has been created for the current user.

400 Bad Request

Failed login: the JSON body was not well-formed, or validation errors occurred.

401 Unauthorized

Failed login: the user credentials were not accepted.

409 Conflict

Failed login: A current session is already in progress for the specified user.

For a successful login (201 Created return code), the body of the response will contain status code, session ID, and URI for the session; additionally, a session cookie is returned. The following is an example.

```
{
  "code": 201,
  "id": "phemi-agile-session:b5a04a2353814a679a9df303a387aca2"
}
```

In this example:

- `code`: is the status code returned by the HTTP request.
- `id`: is the session ID

Usage Guidelines

This example shows Python code that logs a user in, saves the user session cookie, makes a request and logs out.

```
import urllib
import httplib2
import json

http = httplib2.Http()

# Log in
url = 'http://hostname:port/rest/user_sessions'
body = {'username': 'username', 'password': 'password'}
headers = {'Content-type': 'application/json'}
login_response, login_content = http.request(url,
                                             'POST',
                                             headers=headers,
                                             body=json.dumps(body))

# Save the login session cookie into the header for the next
# call
headers = {'Cookie': login_response['set-cookie']}

# Make a REST call and include the login session cookie in the
# header
url = 'http://hostname:port/rest/data_sources/datasource_id/raw_data'
query_response, query_content = http.request(url,
                                             'GET',
                                             headers=headers)

# Log out using the login session cookie in the header
url = 'http://hostname:port/rest/user_sessions'
headers = {'Cookie': login_response['set-cookie']}
logout_response, logout_content = http.request(url,
                                             'DELETE',
                                             headers=headers)
```

User Logout

Log off PHEMI Central and delete the session.

URI

```
DELETE /rest/user_sessions
```

Request Parameters

This request logs the user off PHEMI Central by sending a DELETE request containing the cookie for the user session. request. The DELETE request does not expect a JSON body or any request parameters. However, a cookie that contains the user session information is required.

Request Headers

None.

Response

The following are the HTTP status codes that can be expected:

204 No Content

The session for the current user has been deleted.

404 Not Found

The specified user session does not exist.

Usage Guidelines

This example shows Python code that logs a user in, then uses the login cookie to log the user off.

```

import urllib
import httplib2
import json

http = httplib2.Http()

# Log in
url = 'http://hostname:port/rest/user_sessions'
body = {'username': 'username', 'password': 'password'}
headers = {'Content-type': 'application/json'}
login_response, login_content = http.request(url,
                                             'POST',
                                             headers=headers,
                                             body=json.dumps(body))

# Include the login session in the header
url = 'http://hostname:port/rest/user_sessions'
headers = {'Cookie': login_response['set-cookie']}
logout_response, logout_content = http.request(url,
                                              'DELETE',
                                              headers=headers)

```

Data Ingest

Submit data to PHEMI Central.

URI

```
POST /rest/data_sources/datasource_id/ingestions
```

Request Parameters

This request submits data to PHEMI Central by issuing a POST request to the REST ingest URI. The POST request expects a JSON payload with the Semios device data:

- A version identifier
- A device identifier
- A set of non-hierarchical logs (data)
- A set of non-hierarchical tags

Request Headers

Prefer: respond-async

The presence of the `Prefer` header with the value `respond-async` will cause requests to be executed in the background. Control is returned to the REST client immediately. If this header is used, a return code of 202 Accepted is returned.

Response

The following are the HTTP status codes that can be expected:

200 OK

The ingestion request completed successfully. The raw data has been persisted in PHEMI Central.

202 Accepted

The ingestion request was accepted, but did not complete.

400 Bad Request

The JSON body of the request is not well-formed.

401 Unauthorized

The user session is invalid.

403 Forbidden

The user session does not have permission to perform an ingestion.

404 Not Found

The data source does not exist.

500 Internal Server Error

An internal system error has occurred.

Usage Guidelines

In the event of a 202 `Accepted` return code, the body of the response will contain status and meta information. The following is an example.

```
{
  "_links": {
    "curies": [
      {
        "href": "http://docs.phemi.com/rels/{rel}",
        "name": "ph",
        "templated": true
      }
    ],
    "ph:task_history": {
      "href": "/rest/tms/task_histories/54108814e779891b9b1a1eb4",
      "title": "Ingest and Derive for Data Source ECG"
    },
    "self": {
      "href": "/rest/tms/ingest_statuses/54108814e779891b9b1a1eb4"
    }
  },
  "error": null,
  "result": null,
  "status": "pending"
}
```

If the task is still running, the return status code will continue to be 202 `Accepted`; otherwise, if the task finished and was successful, a 200 `OK` response code is returned. If the task failed, a 500 `Internal Server Error` is returned along with error details in the response body.

In the example below, the task is still running as the status shows on the last line. To determine the status of the ingestion at a later time, use the *self href* link specified in this response. In this example, the following is the link to use to determine the running status:

```
/rest/tms/ingest_statuses/54108814e779891b9b1a1eb4
```

The following is an example of a status while the ingest task is still running:

```
{
  "_id": {
    "$oid": "54108814e779891b9b1a1eb4"
  },
  "_links": {
    "curies": [
      {
        "href": "http://docs.phemi.com/rels/{rel}",
        "name": "ph",
        "templated": true
      }
    ],
    "self": {
      "href": "/rest/tms/task_histories/54108814e779891b9b1a1eb4"
    }
  },
  "action": "chained",
  "error": "",
  "extra_props": {
    "tasks": [
      {
        "_id": {
          "$oid": "54468bb0e779891099693f44"
        },
        "action": "ingest",
        "error": "",
        "extra_props": {
          "data_source_id": "543d87d8e779897cfc5d3330",
          "data_source_name": "Semios Sensors",
          "total_metasize": 212,
          "total_objects": 1,
          "total_rawsize": 780
        },
        "finished": "2014-10-21T16:37:04.576Z",
        "name": "Semios Retention",
        "queued": "2014-10-21T16:37:04.464Z",
        "started": "2014-10-21T16:37:04.498Z",
        "status": "finished",
        "uniquename": "datasource-Semios Sensors",
        "username": "admin"
      },
      {
        "_id": {
          "$oid": "54468bb0e779891099693f45"
        },
        "action": "derive",
        "error": "",
        "extra_props": {},
        "finished": "2014-10-21T16:37:19.683Z",
        "name": "Semios Retention",
        "queued": "2014-10-21T16:37:04.488Z",
        "started": "2014-10-21T16:37:04.583Z",
        "status": "finished",
        "uniquename": "datasource-Semios Retention",
```

```

        "username": "admin"
    }
]
},
"finished": "2014-10-21T16:37:19.686Z",
"name": "Ingest and Derive for Data Source Semios Sensors",
"queued": "2014-10-21T16:37:04.491Z",
"started": "2014-10-21T16:37:04.494Z",
"status": "finished",
"uniquename": "Ingest and Derive for Data Source Semios Sensors",
"username": "admin"
}

```

Notice that the task status is set to “finished” and the time the task finished is also given. If the DPF has not been configured to process the derived data immediately, a finished task only indicates that the ingestion of raw data is complete (the raw data has been persisted in PHEMI Central). To determine when generation of derived data has been completed, follow the instructions in the Derivation Completion section.

Query Sensor Data

Query data from a data source.

URI

```
GET /rest/data_sources/datasource_id/raw_data?attribute-
name__operator=lexicoder:filter-value
```

Request Parameters

This request allows you to query data from a given data source based on various criteria such as attribute values and ranges. Query parameters or values must be correctly escaped for URLs as necessary.

This request supports the following parameters.

attribute-name__operator=lexicoder:filter-value

Queries the specified data source for the specified data. In this parameter:

- *attribute-name*: The raw-data attribute being queried. The attribute name is defined in the DPF for the data source.
- *__operator*: The comparison operator specifying how the query should be performed. Supported operators are listed in [Query Operators](#).
- *lexicoder*: The data type of the queried value. The data type is defined in the DPF that creates the derived data during data ingestion. Supported data types are described in [Data Types in Queries](#).
- *filter-value*: The value to query on. For example, in `/rest/datasources/datasource-id/raw_data?derived:id__eq=STRING:sensor_1138`, the *filter-value* is `sensor_1138`.

skip=num-rows-to-skip

Skips the specified number of rows in the query result and returns subsequent rows in the resultset. Rows are considered to start numbering at 1.

By default, `skip` is 0, which means no results are skipped. Specifying a value for `skip` that is larger than the number of rows in the resultset is not an error, but no results are returned. Specifying a negative value for `skip` is an error, and causes an exception.

As an example, assume a resultset of 50 rows, numbered row 1 to row 50. The results returned for various values of `skip` are shown below.

Table 1: "skip" Parameter Behavior

Value for "skip"	Rows Returned
Undefined	1 to 50
skip=0	1 to 50
skip=1	2 to 50
skip=10	11 to 50
skip=50	None
skip=100	None
skip=-1	Error

The following example skips the first 50 rows of the query results and returns from row 51 onwards.

```
/rest/datasources/datasource-id/raw_data?
derived:id__eq=STRING:sensor_1138&skip=50
```

Note that you can use `skip` parameter in combination with the `limit` parameter to achieve pagination-type functionality; see the `limit` parameter for an example.

limit=max-rows-to-return

Specifies the maximum number of rows to return from the resultset. By default, `limit` is set to 50. The largest value permitted for `limit` is 2500; specifying a larger value is an error.

As an example, assume a resultset of 100 rows, numbered row 1 to row 100. The results returned for various values of `limit` are shown below.

Table 2: "limit" Parameter Behavior

Value for "limit"	Rows Returned
Undefined	100
<code>limit=1</code>	1
<code>limit=2</code>	1 and 2
<code>limit=10</code>	1 to 10
<code>limit=100</code>	1 to 100
<code>limit=200</code>	1 to 100

The following example limits returned results to 50 rows.

```
/rest/datasources/datasource-id/raw_data?
derived:id__eq=STRING:sensor_1138&limit=50
```

The `limit` parameter can be used with the `skip` parameter to select from the resultset in various ways. For example, specifying `skip=1, limit=50` returns rows 2 through 51 of the resultset. Incrementing `skip` by the value of `limit` results in pagination functionality, as in the first two lines of the following example. In this example, assume that the resultset is 100 rows.

```
skip=0,limit=50      # Returns rows 1 to 50
skip=50,limit=50     # Returns rows 51 to 100
skip=75, limit=50    # Returns rows 76 to 100
skip=99, limit=50    # Returns row 100
skip=100, limit=50   # Returns nothing
```

`order_by=comma-separated-list`

Specifies how the returned resultset should be ordered. Order is specified as a comma-separated list of attributes. The hyphen is a reverse-ordering operator: prepending a hyphen ("-") in front of a value reverses the normal ordering of data. For example, if `derived:data|wind_speed` is normally returned in ascending order, `-derived:data|wind_speed` is returned in descending order.

Consider the following request:

```
/rest/datasources/datasource-id/
raw_data?derived:id__eq=STRING:sensor_113&
order_by=derived:data|temperature,-derived:data|wind_speed
```

In this example, the resultset returned by the query would be ordered first by `derived:data|temperature` and then by `derived:data|wind_speed` in reverse order.

The attributes listed in the `order_by` attribute apply only to the rows actually returned by the query. The `order_by` specification has no effect on what rows the query returns, only on the order of the rows returned.

An exception to this behavior occurs when one of the attributes specified for the `order_by` parameter matches an attribute in the query itself, as in the following example:

```
/rest/datasources/datasource-id/
```

```
raw_data?derived:id__eq=STRING:sensor_113&
order_by=-derived:id
```

If a reverse ordering operator is present, as it is in the example, it is the operator is applied first, to make a more efficient query. In this case, the query could potentially return rows from the database in a different order than a query not using the operator.

Request Headers

None.

Response

When an HTTP request is made against the raw data REST interface, the following HTTP status codes can be expected depending on the query result:

200 OK

The query was successful.

400 Bad Request

Invalid criteria parameter values were provided.

401 Unauthorized

The user is not authenticated.

403 Forbidden

The authenticated user is not authorized to perform the query.

404 Not Found

A resource associated with the query (for example, a data source) does not exist.

500 Internal Server Error

An internal system error has occurred.

Usage Guidelines

In the following example:

- The data source ID is 540e5056e77989182bd5aad0.
- The ID of each derived data item takes the form `sensor_n`
- Data is to be returned for `sensor_1130` up to but not including `sensor_1140`.

```
GET /rest/data_sources/540e5056e77989182bd5aad0/raw_data?
derived:id__gte=STRING:sensor_1130& derived:id__lt=STRING:sensor_1140
```

Semios DPF Reference

This section describes the Data Processing Functions implemented to allow Semios to use PHEMI Central.

For information about supported data types, see [Data Types in Queries](#)

DPF Metadata

This section describes the metadata generated when a Semios log entry is processed.

Name	Type	Description
datasource	admin	The identifier of the data source.
document_status	admin	The status of the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
source_of_data	admin	TBD
data:chunks	data	TBD
encoding	data	The encoding algorithm used to encode the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
encryption_key	data	The encryption key used to encrypt the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
encryption_type	data	The type of encryption used to encrypt the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
hash	data	The hash algorithm used to secure the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z

Name	Type	Description
size	data	The size of the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
type	data	The document type. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
asset_type	descriptive	The assigned type of the digital asset. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
asset_type	descriptive	The assigned type of the digital asset. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
name	descriptive	A mnemonic name for the document. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
metadata_checksum	header	A checksum for verifying the integrity of the message. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
process_information	header	???. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z
system_identifier	header	???. Supported values are as follows: <ul style="list-style-type: none"> • X • Y • Z

Name	Type	Description
version	header	The version of software running on the system. Supported values are as follows:

DPF Processed Tags

This section describes the derived data that the Semios DPF extracts from log messages.

Name	Type	Description
id	STRING	The unique identifier of the log message.
log_timestamp	STRING	The timestamp of the message. Log timestamps are received and persisted "as is"; that is, as type STRING. All dates and timestamps must be sent in ISO 8601 format (for example, 2014-06-23T19:35:00-07:00). The PHEMI system also uses this format for aggregations. For aggregations, all dates and times must be local, in order to align with the local time clock, so, for example, a day extends from midnight to midnight local time.

DPF Processed Data

This section describes the data that is processed for Semios log messages.

Name	Type	Description
latitude	DOUBLE	?. Format is XXXX:
longitude	DOUBLE	?. Format is XXXX:
mac	STRING	The Media Access Control (MAC) address of the sending system. Format is a six-octet number expressed in hexadecimal.
timezone	STRING	The timezone of the sending system.

Name	Type	Description
ALGAD	LONG	TBD
ack	LONG	TBD
app_version	STRING	TBD
awake	LONG	TBD

Name	Type	Description
battery	LONG	TBD
bridge_reboot	LONG	TBD
conf	LONG	TBD
dev_installed	LONG	TBD
device_model	STRING	TBD
dew_point	DOUBLE	TBD
env_ambient_temperature_celsius	DOUBLE	TBD
env_ambient_temperature_fahrenheit	DOUBLE	TBD
env_humidity_percent	DOUBLE	TBD
error_code	LONG	TBD
errors	LONG	TBD
event_error	LONG	TBD
firmware_version	STRING	TBD
humidity	LONG	TBD
image_count	LONG	TBD
ir_off	LONG	TBD
ir_on	LONG	TBD
last_error	LONG	TBD
lithium	LONG	TBD
model	LONG	TBD
modem_reboot	LONG	TBD
moisture_0_15	LONG	TBD
moisture_105_120	LONG	TBD
moisture_15_30	LONG	TBD
moisture_30_45	LONG	TBD
moisture_45_60	LONG	TBD
moisture_60_75	LONG	TBD
moisture_75_90	LONG	TBD
moisture_90_105	LONG	TBD
node_missed	LONG	TBD
node_type	LONG	TBD
node_unknown	LONG	TBD
os_reboot	LONG	TBD
os_version	STRING	TBD

Name	Type	Description
rain	LONG	TBD
raw_ambient_temperature	LONG	TBD
raw_board_temperature	LONG	TBD
raw_humidity	LONG	TBD
rte_depth	LONG	TBD
signal	LONG	TBD
solar	LONG	TBD
solar_radiation	LONG	TBD
spray_count	LONG	TBD
spray_on	LONG	TBD
temperature	LONG	TBD
temperature_15	LONG	TBD
temperature_45	LONG	TBD
temperature_75	LONG	TBD
temperature_90	LONG	TBD
thinkness	LONG	TBD
ttl_left	LONG	TBD
upload_time	LONG	TBD
uptime	LONG	TBD
uv_radiation	LONG	TBD
vm_error	LONG	TBD
wetness	LONG	TBD
wet_bulb	DOUBLE	TBD
wind_direction	LONG	TBD
wind_speed	LONG	TBD